

# My Internet Hotel High Speed Internet Access Pre-Paid Card User Guide



## Login Instruction

1. Make sure that the setting of IP address is "Obtain an IP automatically".
2. If Wireless LAN is used, make sure you are connected to "**myinternethotel**" network or enter "**myinternethotel**" in SSID field.
3. Run Internet browser (Internet Explorer, Netscape, etc.)
4. Enter user name and password.

## 24-Hours Customer Support

- Please contact hotel staff for assistance.
- E-mail to [support@myinternethotel.com](mailto:support@myinternethotel.com) for all enquiries and technical questions.

## Wired/Wireless TCP/IP Setup of Window 95/98/ME

1. Select **Start-Setting-Control Panel-Network**.
2. Select the **TCP/IP communication protocol** of the network card, & click "**Properties**".
3. Select "**Obtain an IP address automatically**" & click "**OK**".

## Wired/Wireless TCP/IP Setup of Window 2000

1. Select **Start-Setting-Control Panel-Network** and **Dial-up Connections**.
2. Right click on "**Local Area Connection / Wireless Network Connection**" icon & select "**Properties**".
3. Select **Internet Protocol (TCP/IP)** & click "**Properties**".
4. Select "**Obtain an IP address automatically**" & click "**OK**".

## Wired/Wireless TCP/IP Setup of Window XP

1. Select **Start-Control Panel-Network Connections**.
2. Right click on "**Local Area Connection / Wireless Network Connection**" icon & select "**Properties**".
3. Click the "**General**" icon and select **Internet Protocol (TCP/IP)** & click "**Properties**".
4. Select "**Obtain an IP address automatically**" & click "**OK**".

## Wired/Wireless TCP/IP Setup of MAC Users

1. Open **System Preferences**.
2. Select "**Network**" icon.
3. Under "**Show**" pull down manual, select "**Build-in Ethernet / Airport**".
4. Select "**TCP/IP**", in "**Configure**" pull down manual, select "**Using DHCP**".
5. Click "**Apply Now**".

## Wireless Network Connection (Window XP/2000)

1. Right click on the "**Wireless Network Connection**" icon at taskbar.
2. Select "**View Available Wireless Network**".
3. Select "**myinternethotel**", tick on "**Allow me to connect to the selected wireless network**" & click "**Connect**".
4. Click on the **IE** or **Netscape Communicator** to connect to the Internet.

## Wireless Network Connection (Other than Window XP/2000 default)

1. Activate your third party wireless client manager.
2. Scan for **SSID**; select "**myinternethotel**", and click **connect**.
3. Click on the **IE** or **Netscape Communicator** to connect to the Internet.

## Logging Out From The Internet Access

*User can perform either step to log out from the system*

- Type in **1.1.1.1** in the Address window. This will disconnect the system.
- Enable pop up window for Logging Out. If you've disabled the pop up, please make sure that the pop up is not blocked as you'll not be able to see the Log Out Window.
- Unplug the LAN cable. System will be automatically disconnected after 10 minutes.

Please ensure proper log out when Internet Access is not in use.

If you're still able to access the Internet after logging out, please refer to the above steps to ensure proper logging out.

**No replacement of cards is allowed once the card is being activated.**

## Terms & Conditions

- Usage time will be deducted based on per minute block basis.
- Internet Access Card is non-refundable/non-exchangeable upon purchase.

## Product Of:



**Vector InfoTech**

[www.vectorinfootech.com](http://www.vectorinfootech.com)

**Vector InfoTech Private Limited**